

Go to the VM

Officially supported

testshw

RUNNING

x2 - 4GB - t-cloud-win2019-open-000001


fe80::d43c:2263:cf5e:98a4, 10.40.41.24

huwilers2 May - ID: 256

CPU




Net TX



Memory




Net Download Speed



Net RX



Net Upload Speed



vCenter information

GUEST STATE	running	VMWARETOOLS RUNNING STATUS	guestToolsRunning
VMWARETOOLS VERSION	11265	VMWARETOOLS VERSION STATUS	guestToolsCurrent

Capacity

Storage

Network

Snapshots


Actions

CPU	VCPU	Memory	Cost / CPU	Cost / MByte	
2	2	4GB	0	2.83203e-06	Resize

Real CPU



Real memory



Check if you have snapshots on the VM Go to the snapshot tab and check is the status is “No snapshots to show” You can't extend disk if snapshot are present you need to delete the snapshot first !




RUNNING

x2 - 4GB - t-cloud-win2019-open-000001
 fe80::d43c:2263:cf5e:98a4, 10.40.41.24
 huwilers 2 May - ID: 256









vCenter information

GUEST STATE	running	VMWARETOOLS RUNNING STATUS	guestToolsRunning
VMWARETOOLS VERSION	11265	VMWARETOOLS VERSION STATUS	guestToolsCurrent

 Capacity
  Storage
  Network
  Snapshots
  Actions

ID Name Timestamp Actions

No snapshots to show

Take snapshot

The resize is not available when the vm is ON

Before changing hardware configuration you need to turn of the VM

You can turn off by using SSH or the web interface :

RUNNING

x1 - 2GB - t-cloud-debian10
 10.40.41.18
 huwilers 5m ago - ID: 194









Power off

Turn off option :


- "Send the power off signal" will send a signal to the VM to do a proper shutdown
- "Power off the machine" will power off the machine similar than removing the computer power. This should be use only if the "Send the power off signal" don't work.



The status is now powering off :



Press the refresh button to refresh the status until the status is OFF :



Go to the Storage tab And click on the resize button ()

testshw

OFF

x2 - 4GB - t-cloud-win2019-open-000001

fe80::d43c:2263:cf5e:98a4, 10.40.41.24

huwilers2 May - ID: 256

CPU

Memory

Net RX

Net TX

Net Download Speed

Net Upload Speed

vCenter information

GUEST STATE	running	VMWARETOOLS RUNNING STATUS	guestToolsRunning
VMWARETOOLS VERSION	11265	VMWARETOOLS VERSION STATUS	guestToolsCurrent

Capacity

Storage

Network

Snapshots

Actions

ID	Target	Image / Size-Format	Size	Persistent	Actions	Attach disk
0	sda	t-cloud-win2019-open-000001	-/50GB	NO		

Change the value to the desired size and click Resize

Disk Resize

Disk ID

0



New size

60GB


Cost: 1.40 cost/MONTH

Resize


The vm may briefly turn on to apply the modification and the interface may show the vm running but it's not true. Click on the refresh button



Now you can turn on the vm by pressing the start button



The vm will be in status "Deploying" it's normal



Just click the refresh button  to get the new status

From:

<https://doc.eresearch.unige.ch/> - **eResearch Doc**

Permanent link:

<https://doc.eresearch.unige.ch/iaas/modifyvmdisk?rev=1590495911>

Last update: **2025/06/11 12:27**

